Configuring IMAP/POP on Mobile Devices 2010





Configuring IMAP/POP on Mobile Devices

iPhone/iPad/iPod (All Generations)

- I) On the main screen of the device tap Settings
- 2) Select Mail, Contacts, Calendars
- 3) Tap Add Accounts
- 4) Select Other
- 5) Select Add Mail Account
- 6) In the New Account section fill out the appropriate information

Name: <your name>

Address: <full email address>

Password: <password to the mailbox>

Description: <a description for the account>

7) Choose either IMAP or POP

Incoming Mail Server

Host Name: mail.sh5.cloudhostsite.com

User Name: full email address

Password: mailbox password

Outgoing Mail Server

Hostname: (POP) smtp.sh5.cloudhostsite.com

(IMAP) mail.sh5.cloudhostsite.com

Username: Leave blank

Password: Leave blank

8) Tap Next. Finished.

Droid

- I) On the main screen of the device tap Settings
- 2) Select Accounts & Sync
- 3) Select Add Account
- 4) Select Mail

5) Enter in Username (Full Email Address) and mailbox password, then select Manual Set up

Incoming Server Settings (Choose either POP or IMAP)

Email Address: Full email address

Username: Full email address Password: mailbox password

POP server: mail.sh5.cloudhostsite.com

Security Type: SSL Server Port: 995

6)Tap Next

Outgoing Server Settings (Uncheck Login required)

SMTP Server: (POP) smtp.sh5.cloudhostsite.com

(IMAP) mail.sh5.cloudhostsite.com

Security Type: none

Server Port: 25

7) Tap Next. Finished.

*Note: Some Androids have different ways to set up email. Please refer to your owner manual or contact your wireless provider for proper instructions in setting up your device.

Windows Mobile

- I) Swipe left from the Home screen
- 2) Tap Settings, and then tap E-mail and Accounts
- 3) Tap Add an Account and select Other Account
- 4) Enter your e-mail address and password and tap Sign In Windows

5) Tap Advanced

Account name: name the account

Your name: Type in your name as you would like it to appear.

Incoming e-mail server: mail.sh5.cloudhostsite.com

Account type: Choose either POP or IMAP

User name: Full email address

Password: The password to your mailbox

Outgoing (SMTP) e-mail server: (POP) smtp.sh5.cloudhostsite.com

(IMAP) mail.sh5.cloudhostsite.com

Tap **Advanced** settings and tap to select the boxes Require SSL for incoming mail.

6) Tap Sign In

Blackberry

- I) From the BlackBerry home screen, click BlackBerry Setup > Set up Internet Email > Add An Email Account
- 2) Type your email address and password, and then click Next
- 3) Your BlackBerry will try to set up your email account automatically. If your email account can't be configured automatically, do the following:
- 4) Click I will provide the settings to add this email account
- 5) Scroll down and then click Next
- 6) Select Internet Service Provider Email (POP/IMAP), and then click Next
- 7) Type your full email address for your user name
- 8) Scroll down and type the name of the email server: (mail.sh5.cloudhostsite.com)
- 9) Click Next
- **IO) Enter the name of the outgoing server :** (POP) smtp.sh5.cloudhostsite.com (IMAP) mail.sh5.cloudhostsite.com
- II) Click OK to complete the setup

^{*}Note: Some Blackberry's have different ways to set up email. Please refer to your owners manual or contact your wireless provider for proper instructions in setting up your device.